



1.3	.....	3
3.1	.....	5
3.2	.....	5
4.1 NFC	.....	6
4.2 NFC	LED .....	8
4.3 DALI	NFC .....	9
4.4	.....	12
4.5	.....	15





打开串口连接 ×

端口

波特率

校验位

数据位

停止位

SS=100VP,56BH.

LED DRIVER  
SOSEN

断开  
诊断检测  
读取编程器

写入编程器  
读取LED驱动器

工作电流设定

DIM调光

走时调光

SSA软启动

ELA寿命终结预警

CLO恒流输出


The screenshot displays the SosenProgrammer software interface. At the top, the title bar shows the version and connection details. Below the title bar is a menu bar with '文件', '连接', '语言/Language', and '帮助'. The main area is divided into several sections. On the left, there are three vertical buttons: '断开' (Disconnect), '诊断检测' (Diagnostic Check), and '读取编程器' (Read Programmer). Below these are two more buttons: '写入编程器' (Write Programmer) and '读取LED驱动器' (Read LED Driver). The central part of the interface features six graphs: '工作电流设定' (Working Current Setting), 'DIM调光' (DIM Dimming), '走时调光' (Timing Dimming), 'SSA软启动' (SSA Soft Start), 'ELA寿命终结预警' (ELA Lifetime End Warning), and 'CLO恒流输出' (CLO Constant Current Output). Each graph shows a different waveform or data set. The background of the graphs has a green and blue color scheme with the 'SOSEN' logo.


①

③

④


The bottom part of the screenshot shows red annotations. There are three red circles with numbers inside: '①' is located on the left side, '③' is in the center, and '④' is at the bottom center. A red rectangular box highlights a portion of the interface on the left side, overlapping the '写入编程器' and '读取LED驱动器' buttons.








SosenProgrammer V1.2.23.0425 - [NFC: ID ISC.PRH101-U::29B87331] - [Administrator]


文件 连接 语言/Language 帮助

 连接


 断开

 诊断检测


 读取编程器

 写入编程器

 读取LED驱动器

 写入LED驱动器

## 加载机型默认值



**1. 硬件接线检查:**  
---> 连接LED驱动器调光编程线;  
---> 连接编程器USB线;  
编程器“滴”一声表示正确。

**2. 软件编程操作:**  
---> 点击“连接”;  
---> 点击“读取LED驱动器”或“加载机型默认值”;  
---> 修改参数;  
---> 点击“写入LED驱动器”。

读卡器连接成功。 编程器:无机型 LED驱动器:无机型

